

Setting up HLDS

Installation Grundserver

This is how you install [Counter-Strike 1.5](#) mod, an HLDS server, without [WON](#) on a Linux server:

- The best way is to create a new folder in which the server will be installed. This can be done with `mkdir hlds_l` (just type it on the console and press enter).
- Change to the new directory with `cd hlds_l` Enter.
- It is now time to get all data on the machine with which the server will be installed. For this the following files are necessary:
 1. `hlds_l_3110_full.tar.gz` ([source](#))
 2. `hlds_l_3111e_update.tar.gz` ([source](#))
 3. `cs_15_full.tar.gz` ([source](#))
 4. `nowon2.pl` ([source](#))
- We start by making the Perl script `nowon2.pl` executable. Best with `chmod +x nowon2.pl`
- `unzip hlds_l_3110_full.tar.gz`
- Unpack `cs_15_full.tar.gz` and move the unpacked folder `cstrike` into the folder `hlds_l`
- Unpack `hlds_l_3111e_update.tar.gz` into the `hlds_l` folder. Let the old files be overwritten (it is an update)
- run `perl nowon2.pl hlds_l`
- If you are working on a 64 bit version of Linux, you might need to install the 32 bit version of the `libc6` package (e.g. for Debian that is `libc6-i386`).
- If there were no errors during patching, you are now finished with the installation.

Now the *naked* server with the `cstrike` mod is installed and can be tested:

First Server Test

1. `cd hlds_l`
2. `./hlds_run -game cstrike -nomaster +sv_lan 1 +maxplayers XX +map de_dust`
3. The server should now start and accept connections on the default port 27015.

Installing Mods

Actually the basic server is not a [CS](#) server, but a [Half-Life](#) server, but with the appropriate mod it becomes one. Also the naked server is a bit boring. No server sounds, few administrative possibilities, there are no plugins to keep stats for example. But these mods require the installation of Metamod.

Metamod

The first thing you need is the Metamod. This can be found at <http://www.metamod.org>.

1. Create the folder `addons` (i.e. `cstrike/addons`)

2. Inside this folder create the folder `metamod` with the Metamod in it. Like this:
`cstrike/addons/metamod`.
3. Then open the `liblist.gam` in `cstrike` and delete the entry (or comment it out with `;`):
`gamedll_linux "dlls/cs_i386.so"` and write instead: `gamedll_linux "addons/metamod/dlls/metamod.so"` and save.

That should run the Metamod. Start briefly to test it. The CS server should already name it.

AMXmodx

Unpack `amxmodx-1.60-base.tar.gz` and `amxmodx-1.60-cstrike.tar.gz` to `cstrike/addons/`. Then you only have to add the following to `cstrike/addons/metamod/plugins.ini`:
`linux addons/amxmodx/dlls/amxmodx_mm_i386.so`. Restart the server completely and the AMXmodx will run.

WAN Patch

The server installed in this way is a pure LAN server. This means that the server reacts to connections that do not come from an IP in the local network only with a message that it only allows LAN connections. This can be avoided by patching it. You can either patch it yourself, or use the prepared file.

Manually:

1. Create a file named `nowon.c` with the following content: `int NET_IsReservedAdr(){return 1;}`.
2. The file must now be compiled with the following commands: `gcc -c nowon.c -o nowon.o`
3. Now the file is translated into object code and must be linked: `ld -shared -o nowon.so nowon.o`
4. alternatively use the precompiled `nowon.so`
5. Now the file `nowon.so` has to be placed in the root directory of the server. Of course, it must also be called by the server. To do this, enter the following into the file `hlds_run` after the block with `export`: `export LD_PRELOAD=<Path to Library>/nowon.so`. If the file is in the root directory, corresponding to `./nowon.so` as pathname.
6. The server should now be started with the command line parameter `+sv_lan 1`.

Switch off VAC

Valve Anti Cheat is certainly no longer up to date on CS 1.5 servers. Therefore you can disable it to prevent problems: enter `secure 0` in the `liblist.gam`.

Have the Server be Listed

Previously, servers created in this way were listed via the [World Opponent Network](#), or “WON” for short, which in turn could be queried by CS clients from these servers. The WON servers were shut down by Valve in 2004, so the default addresses used by CS 1.5 no longer work. This gap has been closed by the no-won project, or Steamless project.

To make your server visible for the CS server search, replace the list in `valve/valvecomm.lst` with another one. The new file is available at <http://www.no-won.net/valvecomm.lst>. Replace the old file (you might want to make a backup before, but it is not really useful).

Clients must do the same with the `valve/woncomm.lst` file. After that the server is visible via the usual internal CS server search.

Installing Plugins

1. Download *.sma file and *.amxx file, the *.sma files are the source codes, the *.amxx are the compiled plugins. To use them you only need the *.amxx.
2. Place *.amxx file in `$moddir/addons/amxmodx/plugins` (`$moddir` is the `cstrike` directory for CS)
3. Open `$moddir/addons/amxmodx/configs/plugins.ini`
4. Add a line with `plugin_whatever.amxx`, you can also add comments there if the plugin name is not meaningful anyway.
5. Change map, or restart the server

Now you should be good. In case of problems (e.g. for the wrong amx version), check the `#includes` in the *.sma-file. Maybe there is just something missing.

If `#include <vexd_utilities>` is not available, replace with `#include <engine>`. It is possible that the code of `from vexd_utilities` changed during the conversion to engine (e.g.: `EntVars_Get_Vector` became `entity_get_vector`).

If none of this helps, ask for help in the forum.

For *.sma files there is also a [online compiler](#) available, if no *.amxx file was found.

Plugin Suggestions

- [for further search](#)

Sources

- <https://v5.steamlessproject.nl/index.php?page=stepbystepserver#linux>

[Back to CS 1.5](#)

From:

<https://www.mobile-infanterie.de/wiki/> - **mwohlauer.d-n-s.name** / **www.mobile-infanterie.de**

Permanent link:

https://www.mobile-infanterie.de/wiki/doku.php?id=en:troubleshooting:setting_up_hlds&rev=1660484603

Last update: **2022-08-14-13-43**

